

Email Setup

Bread of Life

Please use your email privileges wisely and follow proper email etiquette (www.emailreplies.com)
Bread of Life Ministries' email resources are provided for church purposes. Bread of Life Ministries maintains the ability to examine any messages stored on its server.

General Setup Instructions

General setup information for connecting to your POP3 E-mail client. Consult your Help menu for your Email Client for detailed instructions on adding an email account:

- Username (userid) = name@bolindy.com
- Password = [if you need assistance, write an email to webmaster@bolindy.com]
- Incoming mail server: mail.bolindy.com
Incoming Server(POP3) port: 110
- Outgoing mail server: mail.bolindy.com
Outgoing Server(SMTP) is 587

To change your password, go to this address:

https://cp.lumasis.net:8443/psoft/servlet/psoft.hsphere.CP?action=change_mbox_password

Outlook Express

1. Open up Outlook Express.
2. Select Accounts from the Tools menu.
3. Click on the Mail tab, and then click on Add/Mail...
4. Type your display name, click Next.
5. Type your email address, click Next.
6. Select incoming mail server as POP3. Set both Incoming and Outgoing mail servers as *mail.bolindy.com*
7. Click Next.
8. Account name is your email address, type your password, click Next.
9. Click Finish.
10. On the Outlook Express Tools menu, click Accounts.
11. Click the Mail tab, and then double-click your e-mail account.
12. Click the Advanced tab. Make sure that the Incoming Server(POP3) is 110 and the Outgoing Server(SMTP) is 587.
13. Click OK

Outlook 2002 (XP) and 2003

1. Open up Outlook.
2. Select Email Accounts from the Tools menu.
3. Select Add a new e-mail account, click Next
4. Select POP3, click Next
5. Under the User Information section type your display name and email address.
6. Under Server Information section type *mail.bolindy.com* for both incoming and outgoing servers.
7. Under Logon Information type your username (email address) and your password.
8. Click More Settings.
9. Click on the Outgoing Server tab and check My outgoing server (SMTP) requires authentication and verify that the radio button Use same settings...is marked.
10. Click on Advanced tab. Make sure that the Incoming Server(POP3) is 110 and the Outgoing Server(SMTP) is 587.
11. Click OK
12. Click Next.
13. Click Finish.

